

## Disconnected 7.5 System Requirements

### Windows XP Professional (Service Pack 3)

- **Minimum Requirements:**

- Intel Pentium 3 compatible processor or higher
- 1.8 GHz
- 1 GB RAM available

- **Optimal Requirements:**

- Intel Pentium 4 compatible processor or higher
- 3 GHz
- 2 GB RAM

### Windows Vista or Windows 7

Vista Service Pack 2 (32 & 64 bit)	Windows 7 (32 & 64 bit)
Home Premium	Home Premium
Business	Professional
Ultimate	Ultimate

- **Minimum Requirements:**

- Intel Pentium 4 compatible processor or higher
- 2 GHz processor
- 2 GB RAM

- **Optimal Requirements:**

- Intel Core 2 compatible processor
- 3 GHz processor
- 3 GB RAM

### General Requirements:

- 4 GB space free on the C drive for each installed instance
- Default Internet Browser<sup>†</sup> set to one of the following:
  - Chrome 12, 13, 14, 15 or 16
  - Firefox 5, 6, 7, 8 or 9
  - Internet Explorer 7, 8 or 9
  - Safari 5, 6 or 7
- Adobe Reader version 8 or greater
- 64 bit Operating Systems are supported

### Required and Included in Install:

- .NET Framework 3.5 SP1
- Apache HTTP Server 2.2
- Microsoft SQL Server 2005 Express Edition

### Windows Updates

It is recommended that you have installed the latest Windows Service Packs and any critical updates that are available before proceeding with the installation of the Disconnected system. Also, you will need to reboot after any Windows updates before running the install.



## Multiple-Instance Installation Support

iPipeline only supports multiple instances of our Disconnected solution installed on the same machine with version 7.3 or higher.

We realize that users are able to have older versions installed with newer versions (for example, a 7.1 instance with a 7.3 instance). This only works when the older version is installed first (if the newer version is installed first, then an older version cannot be installed on the same machine). Please keep in mind, that while this setup may work for some users, iPipeline does not support this setup and configuration.

## # Browser Options

If it is preferred that the iPipeline Velocity Platform Disconnected application use a browser other than the default browser, the following configuration change can be made to specify which browser is used.

### 1. Open the following file in Notepad:

<Install Location>\CossEnterpriseSuite\Exes\AppLaunch.config

### 2. Modify the Browser key as shown below:

- Default                      <Browser>default</Browser>
- Chrome                      <Browser>chrome.exe</Browser>
- Firefox                      <Browser>firefox.exe</Browser>
- Internet Explorer        <Browser>iexplore.exe</Browser>
- Safari                      <Browser>safari.exe</Browser>